

# Source Water Assessment Program (SWAP) Report For

### **Countryside Village Apartments (Draft)**

#### What is SWAP?

The Source Water Assessment Program (SWAP), established under the federal Safe Drinking Water Act, requires every state to:

- ? Inventory land uses within the recharge areas of all public water supply sources;
- ? Assess the susceptibility of drinking water sources to contamination from these land uses; and
- ? Publicize the results to provide support for improved protection.

## SWAP and Water Quality

Susceptibility of a drinking water source does *not* imply poor water quality. Actual water quality is best reflected by the results of regular water tests.

Water suppliers protect drinking water by monitoring for more than 100 chemicals, treating water supplies, and using source protection measures to ensure that safe water is delivered to the tap.

Prepared by the
Massachusetts Department of
Environmental Protection,
Bureau of Resource
Protection,
Drinking Water Program

Date DRAFT Prepared: January 26, 2001

#### Table 1: Public Water System (PWS) Information

PWS NAME	Countryside Apartments				
PWS Address	83 Sturbridge Road Box 4				
City/Town	Charlton				
PWS ID Number	2054038				
Local Contact	John McNeany				
Phone Number	(508) 248-7140				

Well Name	Source ID#	Zone I (in feet)	IWPA (in feet)	Source Susceptibility
Well #1	2054038-01G	204	511	Moderate

#### Introduction

We are all concerned about the quality of the water we drink. Drinking water wells may be threatened by many potential contaminant sources, including septic systems, road salting, and improper disposal of hazardous materials. Citizens and local officials can work together to better protect these drinking water sources.

#### **Purpose of this report:**

This report is a planning tool to support local and state efforts to improve water supply protection. By identifying land uses within water supply protection areas that may be potential contaminant sources, the assessment helps focus protection efforts on appropriate best management practices (BMPs) and drinking water source protection measures. Department of Environmental Protection (DEP) staff are available to provide information about funding and other resources that may be available to your community.

#### This report includes:

- 1. Description of the Water System
- 2. Discussion of Land Uses within Protection Areas
- 3. Recommendations for Protection
- 4. Attachments, including a Map of the Protection Areas

#### 1. Description of the Water System

The well for the facility is located near the facility. The well has a Zone I of 204 feet and an Interim Wellhead Protection Area (IWPA) of 511 feet. The well is located in an aquifer with a high vulnerability to contamination due to the absence of hydrogeologic barriers that can prevent contaminant migration. Please refer to the attached map of the Zone I and IWPA. The well serving the facility has chlorine added as a disinfectant.

For current information on monitoring results and treatment, please contact the Public Water System contact person listed above in Table 1 for a copy of the most recent Consumer Confidence Report.

### What is a Protection Area?

A well's water supply protection area is the land around the well where protection activities should be focused. Each well has a Zone I protective radius and an Interim Wellhead Protection Area (I WPA).

- The Zone I is the area that should be owned or controlled by the water supplier and limited to water supply activities.
- The I WPA is the larger area that is likely to contribute water to the well.

In many instances the I WPA does not include the entire land area that could contribute water to the well. Therefore, the well may be susceptible to contamination from activities outside of the I WPA that are not identified in this report.

#### What is Susceptibility?

Susceptibility is a measure of a well's potential to become contaminated due to land uses and activities within the Zone I and Interim Wellhead Protection Area (I WPA).

#### 2. Discussion of Land Uses in the Protection Areas

There are a number of land uses and activities within the drinking water supply protection areas that are potential sources of contamination.

Key issues include:

1. Inappropriate Activities in Zone Is.

The overall ranking of susceptibility to contamination for the well is Moderate, based on the presence of moderate threat land use or activity in the IWPA, as seen in Table 2.

1. Zone I – Currently, the well does not meet DEP's restrictions, which only allow water supply related activities in Zone Is. The facility's Zone I contains homes, roads and parking areas. The public water supplier does not own and/or control all land encompassed by the Zone I. Please note that systems not meeting DEP Zone I requirements must get DEP approval and address Zone I issues prior to increasing water use or modifying systems.

#### **Recommendations:**

- ✓ Remove all non-water supply activities from the Zone I to comply with DEP's Zone I requirements.
- ✓ Do not use road salt within the Zone I.
- ✓ If the facility intends to continue utilizing the structures, roads, and parking areas in the Zone I, use BMPs and restrict activities that could pose a threat to the water supply.

Implementing the following recommendations will reduce the system's susceptibility to contamination.

#### Table 2: Table of Activities within the Water Supply Protection Areas

Potential Contaminant Sources	Zone I	IWPA	Threat	Comments
Parking lot, driveways & roads	Yes	Yes	Moderate	Limit road salt usage and provide drainage away from wells
Aquatic wildlife	No	Yes	Low	
Structures	Yes	Yes	-	Non-water supply structures in Zone I (three homes)

<sup>\* -</sup>For more information on Contaminants of Concern associated with individual facility types and land uses please see the SWAP Draft Land Use / Associated Contaminants Matrix on DEP's website - www.state.ma.us/dep/brp/dws/.

#### Glossary

Zone I: The area closest to a well; a 100 to 400 foot radius proportional to the well's pumping rate. To determine your Zone I radius, refer to the attached map.

I WPA: A 400 foot to ½ mile radius around a public water supply well proportional to its pumping rate; the area DEP recommends for protection in the absence of a defined Zone II. To determine I WPA radius, refer to the attached map.

**Zone II:** The primary recharge area defined by a hydrogeologic study

Aquifer: An underground water-bearing layer of permeable material that will yield water in a usable quantity to a well.

**Hydrogeologic Barrier:** An underground layer of impermeable material that resists penetration by water.

**Recharge Area:** The surface area that contributes water to a well

#### 3. Protection Recommendations

Implementing protection measures and best management practices (BMPs) will reduce the well's susceptibility to contamination. Countryside Village Apartments should review and adopt the key recommendations above and the following:

#### Zone I:

- ✓ Keep non-water supply activities out of the Zone I.
- ✓ Consider well relocation if Zone I threats cannot be mitigated.

#### **Training and Education:**

✓ Train staff on proper hazardous material use, disposal, emergency response, and best management practices.

#### **Facilities Management:**

✓ Implement standard operating procedures regarding proper storage, use and disposal of hazardous materials. To learn more, see the hazardous materials guidance manual at www.state.ma.us/dep/brp/dws/dwspubs.htm.

#### **Planning:**

- ✓ Work with local officials in Charlton to include the Countryside Apartments' IWPA in Aquifer Protection District Bylaws and to assist you in improving protection.
- ✓ Have a plan to address short-term water shortages and long-term water demands. Keep the phone number of a bottled water company readily available.
- ✓ Supplement the SWAP assessment with additional local information and incorporate it into water supply educational efforts. Use a potential contaminant threat inventory to assist in setting priorities, focusing inspections, and creating educational activities.

These recommendations are only part of your ongoing local drinking water source protection. Citizens and community officials should use this SWAP report to spur discussion of local drinking water protection measures.




Figure 1: Example of how a well could become contaminated by different land uses and activities.

#### 4. Attachments

- Map of the Public Water Supply (PWS) Protection Area.
- Recommended Source Protection Measures Factsheet

#### For More Information:

Contact Josephine Yemoh-Ndi in DEP's Worcester Office at (508) 792-7650 x 5030 for more information and for assistance in improving current protection measures.

More information relating to drinking water and source protection is available on the Drinking Water Program web site at:

www.state.ma.us/dep/brp/dws/

Copies of this assessment have been provided to the public water supplier, town boards, and the local media.

#### **Additional Documents:**

To help with source protection efforts, more information is available by request or online at <a href="https://www.state.ma.us/dep/brp/dws">www.state.ma.us/dep/brp/dws</a>, including:

- 1. Water Supply Protection Guidance Materials such as model regulations, Best Management Practice information, and general water supply protection information.
- 2. MA DEP SWAP Strategy
- 3. Land Use Pollution Potential Matrix
- 4. Draft Land/Associated Contaminants Matrix